

Annexure 2: Live Details

Issue details for live session

Company Name	Larsen & Toubro Infotech Limited
Symbol	LTI
Series	IS (Non retail category) RS (Retail category – Bid value < or = Rs 2 lacs)
ISIN	INE214T01019
Issue Size	Upto 59,00,000 equity shares of Re 1/- each (Base Offer Size) and Upto 46,27,288 equity shares of Re 1/- each (Oversubscription Option). The seller shall intimate the stock exchange of its intention to exercise the oversubscription after trading hours (i.e. on or before 5 pm) on September 03, 2018
Date of Offer	September 03, 2018 & September 04, 2018
Floor Price	Rs 1700
Market Lot	1 Equity share
Tick Size	Rs 0.05

Non Retail category Bidding details (IS Series)

Bidding session Date	September 03, 2018
Bidding session Time	09:15 Hrs to 15:30 Hrs.
Series	IS (Non retail category)
Date to indicate CARRY FORWARD of unallocated Bids in Non-retail category*	September 04, 2018
Carry Forward Timings	09:15 Hrs to 15:30 Hrs.

* Trading members who want to carry forward their unallocated non-retail bids on T+1 shall have to modify such bids and opt to carry forward the bids on the NEAT terminal of IPO. **For further details refer circular NSE/CMTR/31777 dated February 19, 2016.**

Retail category Bidding details (RS Series)

Bidding session Date	September 04, 2018
Bidding session Time	09:15 Hrs to 15:30 Hrs.
Series	RS (Retail category)
Bidding at Cut-off - 'RS'series	Cut-off available - Default option on order entry screen
Reservation portion %	10% of offer size

TAP Parameters for Live

Members have the option to use either of the below TAP versions for connecting to Exchange (Live) environment.

Windows TAP Software:

Sr. no.	Setup Name	Version	OS	Extranet path
1	TAP_1.1.5_Setup.exe	1.1.5	Windows	/Common/IPO-OFS/WinTAP

Linux TAP Software:

Sr. no.	Setup Name	Version	OS	Extranet path
1	TAP_7.0.9_Setup.sh, TAP_7.0.9_SetupFiles.zip	7.0.9	Linux	/Common/IPO-OFS/LinTAP

Configuring TAP Software windows version 1.1.5 & Linux – Version 7.0.9:

New TAP Version	TAP configuration
For Windows – Version 1.1.5	For Windows TAP – <div><div>IPO - Configuration</div><div>Broker ID : <input type="text"/></div><div>TAP Configuration</div><div>Box ID : <input type="text"/></div><div>Local IP : <input type="text" value="0"/> . <input type="text" value="0"/> . <input type="text" value="0"/> . <input type="text" value="0"/></div><div>WAN IP : <input type="text" value="0"/> . <input type="text" value="0"/> . <input type="text" value="0"/> . <input type="text" value="0"/></div><div>TAP Port : <input type="text" value="9604"/></div><div>FIX Port : <input type="text" value="0"/></div><div>Connection Type : <input checked="" type="radio"/> Lease Line <input type="radio"/> VSAT</div><div>Enable TAP Logging : <input checked="" type="checkbox"/></div><div>Host Configuration</div><div><input checked="" type="radio"/> Primary <input type="radio"/> BCP <input type="radio"/> DEV</div><div>TAP will connect to Primary Environment. Select Live or Mock.</div><div><input checked="" type="radio"/> Live <input type="radio"/> Mock</div><div><input type="button" value="Save"/> <input type="button" value="Exit"/></div></div>
Member Code 10	
Member LAN IP	
WAN IP Provided by NSE	
Please select 'Primary'	
Please select 'Live' for connecting to Live environment	
For Linux – Version 7.0.9	For Linux TAP- <div><pre>***** [TAP IPO Configuration Menu] ***** Broker ID.....[16] 1. Local IP.....[] 2. WAN IP.....[] 3. Box ID.....[0] 4. TAP Port.....[9604] - FIX Port.....[0] (Not Configurable). - PRIMARY Configuration. [Current Configuration]. 6. Switch to BCP Configuration. 7. Switch to Development Configuration. 8. Connection Type.[Lease Line] - Enable TAP Logging (Not Configurable). 10. Change Broker ID. - Switch to Live Environment. [Current Configuration]. 12. Switch to Mock Environment. - Save. - Save & exit. 0. Exit. *****</pre></div>
Please select 'Switch to Live Environment'	

Configuring NSE UDP server: (For Broadcast Data Connection)

Receiving Multicast Address	239.50.50.41
Receiving UDP Port	10841

NSE UDP Broadcast Server Configuration v3.04.00

Broadcast Details

Sending Multicast Address

Local IP Address towards Host

Local IP Address towards NEAT

Host	Receiving UDP Port No.	Receiving Multicast Address	Sending UDP Port No.
0	10841	239.50.50.41	<input type="text"/>

Enter Corresponding Receiving Multicast Address.

To be configured at Member's N/W

WAN IP Provided by NSE

Member LAN IP

To be configured at Member's N/W

Input as 10841

Input as 239.50.50.41

Important Instruction

- Members are requested to upload the latest *participant.txt* file of Capital Market segment, which will be available on NSE extranet or internet <ftp://ftp.connect2nse.com> (Path: /Common/ntneat) for live purpose.
- Members may please note that all the eligible trading members of the Capital Market segment will be eligible to participate in the live session using their existing Capital Market user id with default password as “NEATPM”.
- In case of queries, members are advised to contact Toll Free no: 1800 266 0053.